
ESP Vision Installation Instructions:

DOWNLOAD ESP VISION FOR PC OR MAC:

Download your preferred version of ESP Vision (PC or MAC) from the ESP Vision download link:

<http://www.espvision.com/visiondemo.htm>

INSTALLING ESP VISION 2.3 ON A PC:


Once the software and hardware prerequisites have been met, the Vision 2.3 application can be installed. Prior to installation of Vision 2.3, be sure to exit all other applications.

1. After downloading the software, double click on the Vision2Install.exe file to launch the installation wizard.

The Vision 2.3 installer will check your computer system and video card, and then display the welcome screen.

2. The installation wizard displays and End User License Agreement (EULA). Acceptance of the terms within the license agreement is required for installation of Vision 2.3. After reading the EULA, click on the I agree button to continue the installation.


3. Next the installation wizard displays a list of components to install with Vision 2.3. Leave the selections (if any) as default and press "next".



ESP Vision Installation Instructions

4. If the Vision 2.3 component has been selected in the previous step of the installation wizard, then you will be presented with an option to select the installation location. The default or currently installed location is shown. Press the “Next” button to continue the installation process.

5. Next the installation process will prompt you to select a location for selected plug-in components to be installed. If an application can not be found, an error message will be displayed. Press the “Next” or “Install” button to continue the installation process.



6. Once the Install button is clicked, the Vision 2.3 installation application will perform several system checks to verify that the target computer meets the minimum requirements, including DirectX 9.0c. Once the computer and video card pass inspection, Vision 2.3 and all needed library files are installed into the target directory structure.

7. Once the installation is complete you will be prompted to check for updates. Press “OK” to connect to the ESP Vision server.

8. Press the “Close” button when the installation is complete..

The installation will create a new Windows Program Group for **Vision 2.3** as well as place shortcuts for **Vision 2.3** and **Vision 2.3 Update** on the desktop.

ESP Vision Installation Instructions

INSTALLING ESP VISION 3.0 ON A Mac:

Once the software and hardware prerequisites have been met, the Vision 2.3 application can be installed. Prior to installation of Vision 3.0, be sure to exit all other applications.

1. After downloading the software, double click on "installvision3.zip" . to launch the installation wizard.
2. You should now have a new "installvision3" icon on your mac. Open this file.
3. The introduction screen should appear. Press "next"
4. The installation wizard displays and End User License Agreement (EULA). Acceptance of the terms within the license agreement is required for installation of Vision 2.3. After reading the EULA, click on the I agree button to continue the installation.
5. The next screen shows the plugin selection. Leave the selected (if any) as default and press "next".
6. Press "install"

When installation is complete the software will check for updates. Vision3 should now be placed in your applications folder.